

# Kinetic Asset Management User Guide

**Version 2025.1** 

#### Disclaimer

This document is for informational purposes only and is subject to change without notice. This document and its contents, including the viewpoints, dates and functional content expressed herein are believed to be accurate as of its date of publication. However, Epicor Software Corporation makes no guarantee, representations or warranties with regard to the enclosed information and specifically disclaims any applicable implied warranties, such as fitness for a particular purpose, merchantability, satisfactory quality or reasonable skill and care. As each user of Epicor software is likely to be unique in their requirements in the use of such software and their business processes, users of this document are always advised to discuss the content of this document with their Epicor account manager. All information contained herein is subject to change without notice and changes to this document since printing and other important information about the software product are made or published in release notes, and you are urged to obtain the current release notes for the software product. We welcome user comments and reserve the right to revise this publication and/or make improvements or changes to the products or programs described in this publication at any time, without notice.

The usage of any Epicor software shall be pursuant to an Epicor end user license agreement and the performance of any consulting services by Epicor personnel shall be pursuant to Epicor's standard services terms and conditions. Usage of the solution(s) described in this document with other Epicor software or third party products may require the purchase of licenses for such other products. Where any software is expressed to be compliant with local laws or requirements in this document, such compliance is not a warranty and is based solely on Epicor's current understanding of such laws and requirements. All laws and requirements are subject to varying interpretations as well as to change and accordingly Epicor cannot guarantee that the software will be compliant and up to date with such changes. All statements of platform and product compatibility in this document shall be considered individually in relation to the products referred to in the relevant statement, i.e., where any Epicor software is stated to be compatible with one product and also stated to be compatible with another product, it should not be interpreted that such Epicor software is compatible with both of the products running at the same time on the same platform or environment. Additionally platform or product compatibility may require the application of Epicor or third-party updates, patches and/or service packs and Epicor has no responsibility for compatibility issues which may be caused by updates, patches and/or service packs released by third parties after the date of publication of this document.

Epicor® is a registered trademark and/or trademark of Epicor Software Corporation in the United States, certain other countries and/or the EU. All other trademarks mentioned are the property of their respective owners.

Copyright © 2025 Epicor Software Corporation Epicor.

All rights reserved. No part of this publication may be reproduced in any form without the prior written consent of Epicor Software Corporation.

# **Table of Contents**

Setup	5
Creating Asset Registers	6
Creating Asset Classes	8
Entering Asset Groups in Asset Group Maintenance	10
Completing the Detail Information	10
Entering GL Controls for Purchasing Misc Charge/Credits	11
Entering Spread Codes	13
Adding a Spread Code	13
Show me example	13
Adding a Spread Value	14
Specifying Depreciation Methods	15
Understanding Depreciation Method Rules	19
Using Asset Maintenance	22
Creating Assets	22
Updating Asset-specific Information	23
Defining Relationships Between Assets	24
Linking Assets Register To the Asset	25
Importing an External File to Create Assets	27
Exporting Detailed Asset Records to an External File	28
Running the Asset Mass Changes Process	30
Operations	32
Entering AP Invoices	33
Creating New Groups	33
Specifying Invoice Details	34
Creating Lines	36
Adding Miscellaneous Lines	37
Specifying Late Landed Costs from Third Party Suppliers	39
Managing General Ledger Functions	
Allocating Lines to Multiple General Ledger Accounts	
Setting GL Controls	
Adding Deferred Expense Amortization Details	
Adding Amortization Lines	
Making Deferred Expense Amortization Schedules	
Locking/Unlocking a Group	
Posting Invoices to AP Accounts	



Entering Asset Additions	53
Running the Asset Depreciation Calculation Process	56
Entering Asset Disposals	57
Entering Asset Impairments	59
Entering Asset Revaluations	61
Running the Asset Posting Process	64
Closing Asset Period / Year	66
Reports	68
Generating the Asset Depreciation Report	69
Generating the Asset Depreciation Forecast Report	70
Generating the Asset Labels Report	71
Generating the Asset Overview Report	73
Generating the Asset Annual Schedule Report	74



# Setup

This section describes the primary records you need to create for the Asset Management module. These apps are contained within the Setup folder for the module. Only the primary records are described here. Some areas within the Operations section may also document setup records if they are required for a specific workflow.



#### **Creating Asset Registers**

In **Asset Register Maintenance**, create asset registers and link them to General Ledger books, if necessary.

An asset register is a financial view of an asset. A financial view is a group of parameters that control all valuations of the asset and when valuations are recognized.

You create an asset register that contains parameters for depreciation conventions, depreciation methods, production units, estimated life, asset calendar, and so on. Most parameters are specific to an asset and you define them as its properties. You can select only one asset calendar per asset register. All assets included in the register use the same asset calendar.

You need to link an asset to at least one asset register, but you can link each asset to multiple registers. The system records, maintains, and reports all activities controlled by parameters (depreciation, disposal) and amounts that result from these activities per asset register.




You link an asset register to a GL book so it records all asset activities. If an asset is included in multiple registers, different depreciation parameters in the asset registers can affect the values posted in depreciation and disposal transactions.

Use the landing page of the application to view existing asset registers or add a new one.

In this article, we will cover creating an asset register.

- From the main menu, go to Financial Management > Asset Management > Setup > Asset Register.
- 2. Select **New** to create a new record. The **Details** page opens.
- 3. Enter the **Asset Register** identifier and description.
- 4. If you want to make this asset register a default one, select the **Default** check box.





- 5. If necessary, specify the GL book to link the asset register to it. To do that, either enter its name directly in the **GL Book** field or use the **Search** icon to search for the GL book you need.
- 6. The **Calendar** value default from the book you select. You can select another calendar from the drop-down, if you want.
  - For more information on how to set up GL books and fiscal calendars, review the **General Ledger** chapter in the online help.
- 7. Select Save .

#### **Creating Asset Classes**

Asset classes are valuable when you want to group assets together for reporting purposes based on General Ledger (GL) divisions and departments. Asset classes are optional, but highly recommended. They help you to avoid adding a group code for all possible divisions/departments and asset type combinations. You create asset classes in **Asset Class Maintenance**. Asset class holds the GL Control Code for the balance sheet asset account.

The general ledger (GL) control determines the accounts and journal codes used to post transactions to which the asset class applies.

You can associate one or more GL controls with an asset class in this setup program. Each control associated with an asset class record must belong to a different control type. The association allows the use of control values when the record applies to a posted transaction.

For example, the AR Account and AP Account GL control types reference the company entity. You define GL controls based on both types and apply them to Company A in Company Configuration. A transaction that belongs to Company A then posts using the account hierarchy set up for this specific transaction for the Company A business entity. Posting rules use the controls' account references to create the accounts for the company's journals.

You cannot associate GL controls with programs where users select posting accounts when they enter transactions. Examples of this type of program include AP Adjustment and Cash Receipts. The Master Chart of Accounts (COA) defines the accounts available in these programs.

Use the landing page of the application to view existing asset classes or to enter a new one.

In this article, we will cover entering an asset class:

- 1. From the main menu, go to Financial Management > Asset Management > Setup > Asset Class.
- 2. Select New 🕀.
- 3. Enter the asset class ID and the description for this asset class.





- 4. Select Save.
- 5. You are now ready to select the GL control type and code for the asset class. From the Overflow menu \*\*\*\*, select **New GL Control**.
- 6. On the GL Control card, find and select the GL Control Type and the Control Code.
- 7. Select Save.

# Entering Asset Groups in Asset Group Maintenance

Enter groups to organize assets in **Asset Group Maintenance**. Do this for anything that you want grouped, such as site equipment, motor vehicles, or office equipment. Create the group and then select GL controls that define the accounts associated with the group. The GL Controls are used for the journals to post depreciation, asset additions, asset disposals, and asset impairments.

Use the landing page of the application to view existing asset groups or to enter a new one.

In this article, we will cover entering an asset group. First, enter basic information on the Details card. Then select the GL Control card and choose the appropriate GL control or controls.

#### Completing the Detail Information

- 1. From the main menu, go to **Financial Management > Asset Management > Setup > Asset Group**.
- 2. Select **New** to add a new asset group.
- 3. In the Group Code field, enter an identifier for the asset group, such as VEH-LEAS.
- 4. In the **Description** field, enter additional information to describe the group, such as **Leased Vehicles**.
- 5. If necessary, select a category for the group from the **Report Category** drop-down list. This is typically used for the Asset Annual Schedule report to group categories together.
- 6. Select the **Addition Spread** check box if additions or changes to the depreciation of assets are spread throughout the remaining number of periods in a fiscal year.

10





7. Select Save.

#### Entering GL Controls for Purchasing Misc Charge/Credits

The general ledger (GL) control or controls selected on this **GL Control** card determine the accounts and journal codes used to post transactions to which the record applies.

You can associate one or more GL controls with a record in this application. Each control associated with a record must belong to a different control type. The association allows the use of control values when the record applies to a posted transaction.


**Example:** The AR Account and AP Account GL control types reference the company entity. You define GL controls based on both types and apply them to Company A in Company Configuration. A transaction that belongs to Company A then posts using the account hierarchy set up for this specific transaction for the Company A business entity. Posting rules use the controls' account references to create the accounts for the company's journals.

You cannot associate GL controls with applications where users select posting accounts when they enter transactions. Examples of this type of applications include AP Adjustment and Cash Receipts. The Master Chart of Accounts (COA) defines the accounts available in these applications.

#### To add GL controls:

- 1. On the GL Control card, select New
- 2. Select the GL control **Type** that contains the account contexts you need.
- 3. Next use the **Control** field to enter a GL control contained by the selected GL control type.
- 4. Continue to add the GL control types you need for the current company. When you finish, save the changes.







12

#### **Entering Spread Codes**

Spread codes define the time periods for depreciation processing. You enter spread codes and values in **Spread Code Maintenance**.

The purpose of a spread code is to distribute asset depreciation costs per the working days during which you want to charge depreciation.

After creating a spread code, you add spread values.

Use the landing page of the application to view existing spread codes, or to enter a new one.

In this article, we will cover:

- Adding a spread code
- · Adding a spread value

#### Adding a Spread Code

- 1. From the main menu, go to Financial Management > Asset Management > Setup > Spread Codes.
- 2. Select **New** to add a new spread code.
- 3. Enter the **Code** identifier, and **Description**.
- 4. In the **Spread Code Type** field, select whether the spread distributes asset depreciation costs per fiscal **Year**, or per fiscal **Period**.


#### Show me example

In a Period Type scenario, a company is closed two weeks in August, and another two weeks in December. Fewer working days in these months means less use of the assets, and therefore, less depreciation. The spread codes for these fiscal periods should declare fewer days than spread codes for other fiscal periods. You can define the number of days per period that you want to charge depreciation.

13

5. Select the **Calendar** your company uses for assets.





6. Select Save.

#### Adding a Spread Value

- 1. On the **Values** card, select **New** to add a new spread value.
- 2. Enter the spread Value.
- 3. Enter the **Fiscal Year**, and **Period**. If you entered these values manually, the app disables the **Start Date** and **End Date**fields.
- 4. Use the **GlobalFASprdDy**, and **GlobalLock** check boxes to disable, or enable global use of the spread code within your company.



5. Select Save.



# **Specifying Depreciation Methods**

Specify depreciation methods for assets in **Depreciation Method Maintenance**. There are several methods you can use to calculate depreciation. Methods are generally based on either the passage of time or the asset's level of activity (or use). You can also define a custom formula to calculate depreciation.

The application supports the following methods of depreciation:

- · Rate Straight-Line
- · Life Straight-Line
- · Sum of the Years Digits
- · Declining Balance
- · Fixed Amount Per Year
- · Fixed Amount Per Period
- User Formula
- · Spread Code


For a full description of these methods, see the **Understanding Depreciation Methods Rules** article.

Use the landing page of the application to view existing depreciation method or to enter a new one.

In this article, we will cover entering a depreciation method.


- 1. From the main menu, go to Financial Management > Asset Management > Setup > Depreciation Method.
- 2. Select New to add a new depreciation method.
- 3. Enter an identifier for the method in the **Method** field.
- 4. Enter a description of the depreciation method in the **Description** field.
- 5. Select the required charge basis in the **Depreciation Charge Basis** field. Depending on your selection, the system enables the **Annual Charge** or **Period Charge** fields.
  - Annual Calculates the depreciation amount the asset receives for the year and distributes the value per each period (prorating equally or by spread code).
  - Period Calculates the depreciation amount per each individual period.






- 6. Select the method to calculate the depreciation in the **Calculation Method** field. In the **Formula** field, the calculation syntax displays based on the selection made in the **Calculation Method** field.
- Rate Straight Line The annual charge = (Asset Cost Residual Value) \* Annual Depreciation Rate / 100
- Life Straight Line The annual charge = (Book Value Residual Value) / Remaining Years
- Sum of Years Digit The annual charge = (Asset Cost Residual Value) \* Remaining Years as of Beginning of the Year / Sum of Year Digits
- Declining Balance The annual charge = Book Value as of Beginning of the Year \* Annual Depreciation Rate / 100 / Estimated Life Years as of Beginning of the Year
- User Formula The annual charge is derived from your own custom formula. You can also select a pre-defined formula, then select User Formula and adjust it as your own custom formula.
- Use Spread Code The annual charge is taken from the spread codes selected on the asset record in Asset Maintenance.





- **User Formula** The period charge is derived from your custom formula. You can also select a pre-defined formula, select **User Formula** and adjust it as your custom formula.
- **Use Spread Code** The period charge is taken from the spread codes selected on the asset record in **Asset Maintenance**.
- Use Fixed Value The period charge you manually entered in Asset Maintenance.





7. Select the **User Formula** option from the **Calculation Method** drop-down to enter the formula manually. You can also select a pre-defined formula: select the **User Formula** option, adjust the formula, and save it as a custom one.




When defining a custom formula, use a period as the decimal separator and a comma as the separator between formula operands, regardless of regional settings on the server and client.

- 8. If you entered a formula manually, select **Check Syntax** to validate the formula. If there are no errors in the formula, a message displays to confirm the syntax is correct. If the syntax is incorrect, an error message displays showing the incorrect variable.
- 9. If you selected an **Annual** depreciation charge basis, select a period calculation option from the **Period Calculation** field.
- 10. If applicable, define parameters in the Switch to Alternative Method fields.
- 0

Do this if you want to switch to an alternate depreciation method under certain circumstances. Select application conditions from the **Switch to Alternative Method** drop-down. Specify the percentage used to verify if an automatic switch of the depreciation method is necessary in the **Percent** field. Then specify the **Alternate Method** and **Description** fields.

18



11. Select Save

# **Understanding Depreciation Method Rules**

The application supports the depreciation method rules. Expand each section to learn more about them.

This depreciation method uses an annual depreciation charge basis. The annual charge is calculated using the following formula:

#### Annual Charge = (Asset Cost - Residual Value) \* Annual Depreciation Rate / 100

The period charge is calculated by prorating the annual charge using the **Period Calculation** option.

This depreciation method uses an annual depreciation charge basis. The annual charge is calculated using the following formula:

#### Annual Charge = (Book Value - Residual Value) / Remaining Years

Book value is calculated as the difference between the current asset cost and accumulated depreciation as the end date of the period depreciation is being calculated. The period charge is calculated by prorating the annual charge using the **Period Calculation** option.

You purchased a vehicle at a cost of \$17,000 and will depreciate over 5 years. The vehicle has a residual value of \$2000 and depreciates \$3,000 per year.

Book Value - Beginning of Year	Remaining Years	Depreciation Expense	Accumulated Depreciation	Book Value - End of Year
\$17,000	5	\$3,000	\$3,000	\$14,000
\$14,000	4	\$3,000	\$6,000	\$11,000
\$11,000	3	\$3,000	\$9,000	\$8,000
\$8,000	2	\$3,000	\$12,000	\$5,000
\$5,000	1	\$3,000	\$15,000	\$2,000 (Residual Value)

This depreciation method uses an annual depreciation charge basis. The annual charge is calculated using the following formula:

Annual Charge = (Asset Cost - Residual Value) \* Remaining Years as of Beginning of the Year / Sum of Year Digits

Calculate the period charge by prorating the annual charge using the **Period Calculation** option.

Remaining Years as of Beginning of the Year are the number of years remaining for depreciation. The sum of years digits represents the sum of all year numbers over which the asset is depreciated



An asset has an original cost of \$1000, an estimated life of five years, and a residual value of \$100. The asset's estimated life is five years, therefore, the years' digits are: 5, 4, 3, 2, and 1. Sum of the digits: 5+4+3+2+1=15.

Depreciation rates are as follows:

- 5/15 for the 1st year
- 4/15 for the 2nd year
- 3/15 for the 3rd year
- 2/15 for the 4th year
- 1/15 for the 5th year

Book Value - Beginning of Year	Total Depreciable Cost	Depreciation Rate	Depreciation Expense	Accumulated Depreciation	Book Value - End of Year
\$1,000 (Original Cost)	\$900	5/15	\$300 (\$900 * 5/15)	\$300	\$700
\$700	\$900	4/15	\$240 (\$900 * 4/15)	\$540	\$460
\$460	\$900	3/15	\$180 (\$900 * 3/15)	\$720	\$280
\$280	\$900	2/15	\$120 (\$900 * 2/15)	\$840	\$160
\$160	\$900	1/15	\$60 (\$900 * 1/15)	\$900	\$100 (Residual Value)

This depreciation method uses an annual depreciation charge basis. The annual charge is calculated using the following formula:

Annual Charge = Book Value as of Beginning of the Year \* Annual Depreciation Rate / 100 / Estimated Life Years as of Beginning of the Year

The period charge is calculated by prorating the annual charge using the **Period Calculation** option.

The most common rate used is double the straight-line rate. For this reason, this technique is referred to as the double-declining-balance method. For example, a business has an asset with \$1,000 original cost, \$100 residual value, and five years estimated life. To double the rate, use a 200% annual rate. The straight-line depreciation rate equals (100% / 5) 20% per year. After doubling the rate, use a 40% depreciation rate.



Book Value - Beginning of Year	Depreciation Rate	Depreciation Expense	Accumulated Depreciation	Book Value - End of Year
\$1,000 (Original	40%	\$400	\$400	\$600
Cost)				
\$600	40%	\$240	\$640	\$360
\$360	40%	\$144	\$784	\$216
\$216	40%	\$86.40	\$870.40	\$129.60
\$129.60	\$129.60 -	\$29.60	\$900	\$100 (Residual
	\$100			Value)

This depreciation method uses an annual depreciation charge basis.

Define and fix the annual charge in Asset Maintenance.

This depreciation method uses a periodic depreciation charge basis. The period charge is a fixed value and is entered in **Asset Maintenance**.

You can define a custom formula to calculate depreciation in **Depreciation Method Maintenance**. The formula can consist of multiple arithmetic operators and operands (Estimated Life, Asset Cost, Residual Value, Book value at the beginning of the year, and Depreciation Rate). Validate the formula you entered and edited in a text box and the formula's syntax using **Check Syntax**.

You can use a spread code to distribute asset depreciation costs for established periods, such as the actual working days of a fiscal period. Use Spread Code Maintenance to create spread codes and spread code values.

You can also create methods based on two calculation methods by using the Switch to Alternative Method field.

This functionality may help you create a method such as **Declining Balance to Straight Line** or **MACRS (USA)**, which uses the Declining Balance calculation method until the calculated amount using the **Life Straight Line** method is more than the calculated amount using the **Declining Balance** method. At this point, the system switches to calculating depreciation using the **Life Straight Line** method. To do this, you first create a depreciation method based on the Life Straight Line calculation method. Then you set up a method with **Declining Balance as the Calculation Method**, select **On Greater Expense** from the **Switch to Alternative Method** drop-down, and in the **Method** field, enter your **Life Straight Line** depreciation method



#### **Using Asset Maintenance**

In business and accounting, assets are everything of value that is owned by a person or company. The company's balance sheet displays the monetary value of the assets owned by the company.

Enter and update records for fixed assets using **Asset Maintenance**. Here you can organize assets by group, class, and project, import, export, and duplicate assets, specify an asset register for each asset. Identify the depreciation, cost information, annual charges, period charges, and prorate options for the asset. You can also establish parent/child relationships between assets. If you would like, you can add a photo of the asset to the record.

Use the landing page of the application to view existing assets or to enter a new one.

In this article, we will cover:


- Creating Assets
- Updating Asset-specific Information
- Defining Relationships Between Assets
- Linking Assets Register To the Asset
- Importing an External File to Create Assets
- Exporting Detailed Asset Records to an External File

#### **Creating Assets**

- From the main menu, navigate to Financial Management > Asset Management > Setup >
  Asset.
- 2. Select **New** to add a new asset.
- 3. Enter the Asset Number identifier and its description.
- 4. Select the **Asset Group** for the asset.
- 5. Select the Acquired drop-down list to select the date you gained the asset. The date also displays in the Placed in Service field.
- 6. If you need, select the **Place in Service** drop-down list to select a different date. This date serves as the first date of depreciation.



7. Optionally, select an **Asset Class**. Asset classes are valuable to group assets together for reporting purposes.




- 8. Select Save.
- 9. Select **Duplicate** from the Overflow menu, if needed, to duplicate the asset record.

#### **Updating Asset-specific Information**

Expand the **References** card to update asset-specific information. This card is useful for documenting the asset's origin and viewing relevant information such as suppliers, purchase orders, and job numbers.

To link an asset register to the asset:

- 1. On the **References** card, select the supplier, purchase order, invoice, job for the asset.
- 2. Specify the manufacturer, model, serial number, and other information as needed.



3. Select Save.

#### **Defining Relationships Between Assets**

Use the Parent / Child card to define relationships between assets.

Here you can select a parent asset and then add or remove children for that asset. A parent asset can have multiple child assets. Assets displayed on the **Child Assets** grid can be processed with the current asset record.

To add child assets to a parent asset:

- 1. On the Parent / Child card, select New to add a new child asset.
- 2. Specify the number





3. Select Save.

#### Linking Assets Register To the Asset

You can link an asset to an asset register to control all valuations of the asset and also to control when valuations are recognized.

To link an asset register to the asset:


- 1. On the **Register** card, select **New** to add a new asset register.
- 2. Select icon in the Asset Register column. The **Register Details** card displays.
- 3. Select the **Register** search button of to find and select the asset register.
- 4. Select the **Method** search button of to find and select the depreciation method to use for the asset.
- 5. Select the depreciation Convention you want to use with this asset register. These conventions define how the depreciation amount for the first year is adjusted. Available conventions:
  - Half-year The asset was placed in service at the midpoint of the fiscal year.
  - Mid-month The asset was placed in service in the middle of the fiscal period.
  - Quarter Each quarter is one fourth the total number of periods.
  - Mid-quarter The asset was placed in service in the middle of the quarter.
  - **Full-month** The asset was placed in service during the first half of the fiscal period and the application assumes it was acquired at the beginning of the period; otherwise, the application assumes the first day of the next period.



- Entire-Month The default option, this convention indicates that regardless of what day
  the asset was placed in service, a full period's depreciation is calculated against the
  asset.
- Next Month Depreciation begins in the period after the asset was placed in service.
- Service Date This convention is used to calculate depreciation for the first period. The
  days remaining in the period are divided by the total days in the period to calculate the
  depreciation amount.
- Acquisition Date The acquisition date is used to calculate depreciation for the first period. The days remaining in the period are divided by the total days in the period to calculate the depreciation amount.
- 6. Select one of the following depreciation options for the period of disposal from the Depreciation on Disposal field:
  - Pro-rated to disposal date Calculate depreciation based on depreciation convention.
  - Full Month Always apply full month of depreciation.



• None - Do not depreciate asset at all.



7. Select Save.


# Importing an External File to Create Assets

Use the **Import** option of the Overflow menu to import an external file to create asset or asset addition records. This functionality is useful if you have an asset group from an external system that you wish to bring into the application. The file you import must be a comma delimited file (csv) and follow the import file template.



To import an external csv file:

- 1. Select **Import** from the Oveflow menu. The **Import Asset Group** window displays.
- 2. Select the Input File Namesearch button to find and select the csv file you want to import.



3. Select Import. The Import Successful message displays.




If an error occurs during the import process, a message displays saying some of the assets were not imported. Refer to the error details that display in the **Error Log** field.

#### Exporting Detailed Asset Records to an External File

Use the **Export** command to export detailed asset records to an external file. The file you export is saved as a comma delimited file (csv) and can be updated by using Excel.

- 1. Select **Export** from the Oveflow menu. The **Export Asset Group** window displays.
- 2. Select the **Output File Name** search button to find and select the directory where you want to add your file; enter a file name.





3. Select Ok. The Import Successful message displays.



For more details on the fields, use the field help available in the **Help & Support** panel of the application.



# Running the Asset Mass Changes Process

The **Asset Mass Changes** process enables you to select a particular set of assets from the database, define the desired changes on those assets, and make those changes online or in the background using scheduled processing.

You can select the assets, asset group, or asset class that need to be modified by using the Filter sheets and specifying replacement values to be assigned to the selected assets. If a field is left empty within the program, the field will not assign a value to the selected assets. In other words, it is not possible to assign an empty value to an asset using Asset Mass Changes.

If you change the parameters for an asset that has posted activities, you may need to create manual GL Journal entries to move asset costs.

#### The **Selection** parameters include:


- Filter Select specific Assets, Asset Groups and Asset Classes to run the process for.
- Schedule Define when to run the process. If you select something other than Now, the Recurring check box is available.
- Recurring Select this check box if you want the report to run on a repeating basis.

#### To run the process:

- 1. Open the **Asset Mass Changes** app.
- 2. Select the fields you want to replace by the process.



When you select the required fields, their replacement fields become available in the form. Fill them in with the replacement values you want to assign during the process.






Select status of the asset for which you want to run the process.





4. Select the **Include Child Assets** check box to include all child assets for the selected asset even if they do not match the selection criteria.



- 5. Expand the Filter card to select specific asset, asset group, and asset class.
- 6. Use the Advanced card to define when you want the process to run. If you select something other than **Now**, the **Recurring** check box is available.
- 7. Select **Process**. 🐾



# Operations

Delete this text and replace it with your own content.




# **Entering AP Invoices**

Entering AP invoices is very important process in closing the financial deals of your company. You buy things and you need to pay for them, you have to meet your terms with the suppliers, get discounts and keep close track of all these transactions. To record payments to your suppliers use the **AP Invoice Entry** app. The invoices you enter here update open purchase orders, shipping receipts, and General Ledger accounts.



To enter an AP invoice, you must install the **Accounts Payable** license.

You can use this app to create both regular invoices and debit memos. Within regular invoices, each line must be assigned a specific type.



In this article, we will cover:

- Creating New Groups
- Specifying Invoice Details
- Creating Lines
- Managing General Ledger Functions
- Adding Deferred Expense Amortization Details
- Locking/Unlocking Group
- Posting Invoices to AP Accounts

#### **Creating New Groups**

Start with creating a new group. A group is a batch of invoices that you collect and post to the 'General Ledger'. Once you create the group, you then enter or generate invoices to process through this group.

To create a group:



- 1. Open the AP Invoice Entry app.
- 2. To add a new group, select **New Group**.

The **Group** field is now ready for entry.



- 3. Enter a name for the group.
- 4. Select the **Apply Date** drop-down list to define the default fiscal period to which group transactions post.

The company's default fiscal calendar determines the values that display in the **Fiscal Year** and **Period** fields.



5. Select Save.

#### Specifying Invoice Details


Enter invoice header information. Here you add or edit miscellaneous charges placed against the current invoice, enter sales tax information, and define an invoice as a recurring source invoice.

- 1. Locate the **Invoices** card.
- 2. Select New Invoice.

The **Invoice Header** card displays.

3. Enter the Supplier, Invoice, Invoice Date, and the Amount.






4. Use the **Payment Method** field to select the default method for remitting payment to this supplier.



5. Select the **Hold Invoice** check box to block posting of the invoice. Select this check box when the invoice is disputed or when you need supervisor approval.





6. If the **Site** field is visible, select a site.



This field is only available/visible if you select the 'Use Multi-Site Processing' check box located on the 'General' card of the 'Company Configuration' app. You must also select the 'Site Segment' check box for a segment using the 'Chart of Accounts Structure Maintenance' app.

- 0
- After you create an invoice line, you will see an entry on the 'GL Analysis' card. The account assigned to this record has the site segment replaced with the site segment for the site you selected in the 'Site' field. For example, a assume a scenario where you are entering an invoice in the 'Main' site but you select the 'Evanston' site in this field. If the default account would have been 2000-00-00, and the site segment value for 'Evanston' is 01, then the account you would see instead is 2000-01-00.
- 7. Select Save.



After you save the invoice the payment schedule is generated based on the purchasing terms. Use the **Payment Schedule** grid to edit, and review the schedule through which you will pay the amount on an AP invoice. The Days Before Due and Discount Percent columns are available only if an option that uses the 'By Schedule' Discount Type is selected in the Terms field on the Invoice Header card.

#### **Creating Lines**

After the invoice header information is complete, add detail lines to it. These detail lines can be different line types - depending on the reason for the payment.

The available line types include:

- Receipt Line Add this type for lines linked to receipts. These receipts are created through the Shipping/Receiving module.
- Miscellaneous Line Use this type for miscellaneous expenses or as a recurring source invoice to use as a template for other recurring invoices; this line type is not linked to purchase orders or job records.
- Job Miscellaneous Line- Use this type to record miscellaneous charges for materials used on specific jobs.

36

Advanced Billing Line - Use this type when you make an advance payment against a
purchase order line before you receive a shipment from the supplier.



- Unreceived Billing Line Use this type when you make a payment against a shipment that is sent out, but is not yet received by your company.
- Asset Line Use this line type to specify relevant information after the purchase of an asset. In this section, we will cover:
  - Adding Miscellaneous Lines
  - Specifying Late Landed Costs from Third Party Suppliers

### Adding Miscellaneous Lines

This example shows you how to enter a **Miscellaneous Line** type. Typically, you create miscellaneous line invoices to account for miscellaneous expenses that are not linked to any purchase order or job records. You can also define a miscellaneous line invoice as a recurring source invoice to use as a template for other recurring invoices.




The **Recurring** check box must be selected and a **Cycle Code** set on the Header card or an invoice with a miscellaneous line to be designated as a recurring source invoice.

To add a miscellaneous line:


1. In the Nav tree, select the Line/Detail node.

The Line Detail card displays.




- 2. On the card, select **Misc Line**.
- 3. Search for and select a part.






- To locate the 'Invoice Information' group box, you must scroll down on the 'Line Detail' card.
- 4. Enter the Supplier Qty and Unit Cost.



5. Select Save.



### Specifying Late Landed Costs from Third Party Suppliers

Landed costs are any additional, unallocated expenses you must include with the cost of purchased materials. Commonly, the total cost of a landed shipment includes the purchase price, freight, insurance, and other costs up to the port of destination that cannot be handled through labor or burden calculations. In some instances, it may also include the customs duties and other taxes levied on the shipment.

In some countries, it is common for simple domestic receipts to have freight charges added from a third-party supplier. Since all costing has to be done on the basis of actual received invoice documents and not by adding an estimated charge, this means that many receipts need to use this feature to add a freight charge at a later time.


For example, you can enter an invoice from a third party supplier, Dane Transportation Company, related to an inventory purchase order (PO) receipt without using Landed Costs and having Late Costs update the average or FIFO cost layer for the parts received on the PO receipt.

To specify late landed costs from 3rd party suppliers and allocate them to received goods:

1. In the Nav tree, select the AP Invoice node.

The **Invoice Header** card displays.






2. Scroll down to locate and expand the 3rd Part Late Cost card.



3. Select **New Late Cost** in the **Late Cost Lines** card.





You can also automatically add Late Costs related to container shipments or purchase receipts to the AP Invoice.

# Show me how to automatically transfer Late Costs related to container shipments and purchase receipts


All late costs related to a container shipment or purchase receipt can be automatically added to the AP Invoice using the Get Late Costs function. You can select one, many or all late costs for multiple containers or receipts related to the supplier on the invoice.

- 1. From the Overflow menu \*\*\*, select **Get > Get Late Costs**.
- 2. The AP Invoice Add Late Costs sliding panel displays.
- On the Receipts/Containers card, review the list of purchase orders with uninvoiced receipts and containers for the supplier and select the one for which you want to get late costs.






- 4. The Late Cost lines that have not been invoiced display on the Late Cost Lines card.
- 5. Select the line(s) you want to invoice or use the **Select All** button.




- 6. Once selected, the Late Cost lines move down to the Selected Late Costs card.
- 7. To generate the Late Cost lines, select the **Generate Late Costs** button at the bottom right-hand corner of the sliding panel.





- 8. Select **OK** to the **Late Costs have been created** message.
- 9. The lines pulled in from the selected PO now display in the Late Cost Lines card.
- 4. Select a Charge Code.
- 5. Specify the **Type**.
- 6. Select the Supplier field to search for and select a supplier.





- 7. Select **Add to Allocation Grid**. The grid displays only received lines available for allocation.
- 8. Select the lines for allocation using the **Selected** check box in the grid. All received receipt lines are added to the **Allocated Lines** grid.
- 9. Select the Allocate Cost button in the Lines To be Allocated card.

Allocations are recalculated. Cost is allocated between the selected lines (unselected lines are ignored) in proportion to the line value according to the disburse method. The application shows the **Allocated Amount**.

### Managing General Ledger Functions

In this section, we will cover:

- Allocating Lines to Multiple General Ledger Accounts
- Setting GL Controls

### Allocating Lines to Multiple General Ledger Accounts

Distribute the current line amounts to specific **General Ledger** accounts. This functionality enables you to update the GL distribution amount, and allocate to multiple GL accounts. This distribution creates the expense offset to Accounts Payable for each invoice line.

You can also distribute these amounts across multi-company accounts and select the external company and GL account that will receive the AP allocations. After you post the AP invoice, the subsidiary (child) company will receive the allocations through a **GL Journal Entry**.



To allocate the allocate expense amounts to more than one GL account:


- 1. Open Invoice Lines > Detail > GL Analysis and specify the GL account for distribution in the GL Account field on the G/L Distribution card .
- 2. In the Nav tree, select the Lines/Detail node.

The Line Detail card displays.



- 3. Scroll down to locate and expand the GL Analysis card.
- 4. Enter the amount you want to apply to this account in the **Document Amount** field.





5. Select Save.

### Setting GL Controls

The general ledger (GL) control or controls selected on this GL Control card determine the accounts and journal codes used to post transactions to which the record applies.

You can associate one or more GL controls with a record in this setup program. Each control associated with a record must belong to a different control type. The association allows the use of control values when the record applies to a posted transaction.


- For example, the AR Account and AP Account GL control types reference the company entity. You define GL controls based on both types and apply them to Company A in Company Configuration. A transaction that belongs to Company A then posts using the account hierarchy set up for this specific transaction for the Company A business entity. Posting rules use the controls' account references to create the accounts for the company's journals.
- You cannot associate GL controls with programs where users select posting accounts when they enter transactions. Examples of this type of program include AP Adjustment and Cash Receipts. The Master Chart of Accounts (COA) defines the accounts available in these programs.

To add GL controls:



1. In the Nav tree, select the AP Invoice node.

The **Invoice Header** card displays.



2. Scroll down to locate and expand the GL Control card.



- 3. On the **GL Control** card, select **New**.
- 4. Select the **GL Control Type** that contains the account contexts you need.



- 5. Next use the **Control** field to enter a GL control contained by the selected GL control type.
- 6. Continue to add the GL control types you need for the current company. When you finish, select **Save**.

### Adding Deferred Expense Amortization Details

In this section, we will cover:

- Adding Amortization Lines
- Making Deferred Expense Amortization Schedules


### **Adding Amortization Lines**

You can create, delete and auto-complete amortization schedules for invoice lines.

To add a new amortization line:

1. In the Nav tree, select the Lines/Detail node.


The Line Detail card displays.



2. Scroll down to locate and expand the **Amortization** card.



3. Select **Deferred Expense** check box.



- 4. Specify the Amortization code field.
- 5. Specify the **Deferred Expense GL Account**.
- 6. Select the Create button.
- 7. Select Save.

### Making Deferred Expense Amortization Schedules

You can also use **Deferred Expense** of the Overflow menu to perform actions with deferred expense amortization schedules for all invoices in the selected invoice group.

You can choose from the following actions:

- **Generate Amortization Schedule** Generate a schedule for all invoices in the selected invoice group.
- Restore Amortization Schedule Overwrite a manually entered schedule line and restore the originally generated schedule.
- Delete Amortization Schedule Delete amortization schedules for all invoices in the group.




### Locking/Unlocking a Group

You can manually lock/unlock a group to make it available for other users. For example, a user need to review/print the 'Group Edit List' for a particular group. If you attempt to open a group that is locked by a certain user, Kinetic displays a message informing you the group is locked by a specific User ID.

1. If you are creating a new group, the In Use By field displays the user ID that created the group.

In this case, the group was created by the 'MANAGER' user. However, this is just an example.



2. Select Unlock Group.


The group is now unlocked.

3. If you want to lock/unlock a specific group, select the **Groups** button.



The Group panel opens.

4. Inside the panel, highlight the group in the grid, and select the **Unlock/Lock** button.



### Posting Invoices to AP Accounts


To finish the **AP Invoice Entry** process, you must post the invoices to the AP accounts within the General Ledger. When an entry group is posted, transactions update the AP information for each supplier referenced within the group.




Once you post the invoices, you can no longer edit or delete them. You can place a posted invoice on hold. If you post an invoice in error, you can enter offsetting transactions. You can also use Invoice Adjustment to write it off, or create and apply debit memo to close the invoice. If you need to adjust the amount of the invoices, you can create a correction invoice.

Use the AP Invoice Entry app to modify the invoice number of any recurring invoice prior to posting:

- 1. Open the AP Invoice Entry app.
- 2. Select a group of recurring invoices.
- 3. Select any recurring invoice that hasn't been posted yet.



4. Select the Change Invoice Number button in the top right corner of the Invoice Detail card.





5. On the Change Invoice Number panel enter your custom invoice number in the **New Invoice Number** field.




6. Select OK.

You can see your new invoice number in the Invoice field on the Invoice Detail card.

To post an entry group:

1. Select Group Post. \*\*

The AP Invoice Post Process panel opens.




- 2. Select **Post** to post the group. The application displays an error message if the group contains invalid entries.
  - If posting errors occur, select the **Group > Posting Log** card to review an error log. Use this log to locate the errors. You can re-post the group after correcting them.

### **Entering Asset Additions**

Enter cost or depreciation additions to assets in Asset Addition Entry.


A **Purchase** asset addition uses the AP interface to select an AP invoice with an Asset line. A **Transfer** asset addition uses the inventory interface allowing you to transfer or create an asset from stock. You can enter details not related to any specific interface with a **Miscellaneous** addition type.

- 8
- An asset addition must not be entered earlier than the acquisition date of an asset.
- 1. Open the **Asset Addition Entry** app.
- 2. In the **Asset** card, select the **Asset Number** for which you want to enter the addition.
- 3. Select New on the Asset Addition card to add cost addition for the selected asset.
  - If you created and received an asset purchase line via the **Purchase Order Entry** and **Receipt Entry**, Kinetic automatically generates a miscellaneous asset addition in the **Asset Addition Entry** app. You can select it from the **Asset Addition** card.




The **Addition Details** card displays, including the addition's purchase order and receipt details.





- 4. Select the Addition Type. Depending on the Addition Type you select, several fields activate.
- 5. Enter the Addition Cost and the Grant Increase amounts.
- 6. When you finish, select the **Ready To Post** check box.



7. For the **Miscellaneous Addition** type, tick the **Inter-Group** check box to transfer assets depreciated in a sister company. Register section populates all asset registers in which the




asset is included. An inter-group addition brings in the cost and the accumulated depreciation for previous and current years from an addition from another company into the system.



An inter-group addition is not posted; it is used only to update the asset master and make the asset available for further depreciation.

- 8. In the **Register List** grid select the **Asset Register** in which the asset is included.
- 9. In the Register Details card, you can also use the Asset Life section to specify whether the new addition extends estimated asset lifetime. Adding more estimated years or periods affects depreciation calculation.



Select the Includes Current Period Depreciation check box in order for CY Depreciation value to include depreciation for the period of addition.

If required, the system makes an adjustment, so that the amortization for the period corresponds to the amortization calculated according to the selected depreciation method. Note, that the adjustment will be made only during the next recalculation.

10. Select Save.





# Running the Asset Depreciation Calculation Process

Run the **Asset Depreciation Calculation** process to calculate the depreciation of assets for the current year, current period, or for an asset's useful life. You can run the process as many times a month as necessary.

Through this calculation, depreciation charges are determined for all registers in which an asset is included. This calculation uses the asset calendar linked to the register.

#### To run the process:

- 1. From the main menu, go to Financial Management > Asset Management > General Operations > Asset Depreciation Calculation.
- 2. Select the **Calculate Option** you need with the asset. Available options include **Current Period**, **Current Year**, and **Asset's Useful Life**.
- 3. Select the **Include Child Assets** check box to include all assets linked to a parent asset in the calculation.
- 4. Select the **Include Assets Marked for Automatic Recalculation** check box to add assets selected for recalculation in the calculation.
- 5. If necessary, filter by **Asset Group**, **Asset Class**, **Individual Asset**, **Asset Register**, or by **Depreciation Method**.
- 6. Select **Process**.



# **Entering Asset Disposals**

Enter cost or depreciation disposals to fixed assets in **Asset Disposal Entry**. In this application, create an asset, record new asset disposal activity, or adjust, delete, and view any unposted asset disposal activities.

Three disposal types are available:

- Miscellaneous a disposal that does not interface with another application
- Transfer a disposal that interfaces with Inventory
- Sale a disposal that interfaces with Accounts Receivable

You can dispose an asset in full or partially. Before you can record a disposal of an asset that has not been fully depreciated, you must calculate the depreciation for the period when the asset is being disposed.

When a partial disposal is created, the system suggests the amount of accumulated depreciation to use in determining the net book value of the partially disposed asset, per asset register. If a company disposes of a long-term asset for an amount different from its book value, an adjustment must be made to net income on the cash flow statement.

For example, a company sells one of its delivery trucks for \$3,000. That truck is shown on the company records at its original cost of \$20,000 less accumulated depreciation of \$18,000. When these two amounts are combined or netted together, the net amount is known as the book value (or the carrying value) of the asset. In the example, the book value of the truck is \$2,000 (\$20,000 - \$18,000). Because the proceeds from the sale of the truck are \$3,000 and the book value is \$2,000, the difference of \$1,000 is recorded in the account Gain of Sale of Truck income statement account. The transaction has the effect of increasing the company's net income. If the truck had sold for \$1,500 (\$500 less than its \$2,000 book value), the difference of \$500 would be reported in the account Loss on Sale of Truck and would reduce the company's net income. When a new asset disposal is entered, the full disposal cost defaults into the Disposal Cost field on the Disposal Detail card.

#### When Depreciation is Already Posted in Future Periods


You can enter and post a disposal when depreciation is already posted in future periods. The next time depreciation is re-run for the same year, it generates a catch-up transaction if the Retrospective Adjustment check box is selected in Asset Maintenance and the Depreciation Method is annual based. If it was a full depreciation, then the catch-up transaction will effectively reverse depreciation in periods after disposal. If the method is period based, there will be no catch-up transactions and you must reverse or reduce depreciation manually in the general ledger.

Use the landing page of the application to view existing asset disposals or to enter a new one.

In this article, we will cover entering an asset disposal.



- 1. From the main menu, navigate to **Management > Asset Management > General Operations** > **Asset Disposal Entry**.
- 2. From the landing page, select the asset for which you want to enter a disposal. Details about the asset display in the Description, Asset Group, Asset Class, and other fields.
- 3. Select **New** to add a new disposal.
- 4. Enter a description for the disposal in the **Description** field.
- 5. Enter the cost in the **Disposal Cost** field. This value defines the cost of an asset at which it should be disposed. This can be the total cost of the asset as well as its part in case of partial disposal. When you depreciate multiple physical assets under the same asset number and only one of them gets disposed, the part of the cost that corresponds to that asset should be subtracted.
- 6. Enter the **Proceeds** value. This field defines the sales amount of the disposal.
- 7. Select Ready to Post.



8. Select Save.



# **Entering Asset Impairments**

You can enter impairments against an asset using Asset Impairment Entry.


An impaired asset is an asset where the market value fell below the carrying amount and is not expected to recover or the asset's market value is less than the book value of the asset. Future cash flows generated from the asset are less than the net difference of the market value and the book value of the asset.

You must record the value of the asset in the books by debiting a loss account, and this loss account displays as an expense in the income statement - crediting the respective asset account.

You can create asset impairments for assets not fully disposed with a status New or Active. By default, the impairment cost is entered using the company's base currency, which is the transactional currency for this transaction. Amounts in reporting currencies are derived using conversions on the Apply Date; however, you can override these converted values manually. Any unposted impairment can be adjusted or deleted.

In this article, we will cover creating using the Asset Impairment Entry application.


- From the main menu, navigate to Financial Management > Asset Management > General
   Operations > Asset Impairment.
- 2. Select an asset in the Asset card.



- 3. Select **New** ① on the **Impairments** card to add the impairment for the selected asset.
- 4. Enter the Impairment Cost.



5. Select the **Ready To Post** check box to indicate this impairment will be included in the asset posting process.



6. Select Save.

# **Entering Asset Revaluations**

You can use Asset Revaluation to periodically revalue your assets so they have the correct value in asset reports, trackers, and financial statements.

When you revalue an asset, it involves the accumulated depreciation of the asset. The system applies this to the asset cost. It then uses the value in the net book value calculation on the cost account to produce the new book value.

If the company chooses the revaluation accounting model for a group of assets, the system periodically revalues those assets. This may change the asset carrying value. When a revalued asset is disposed, the balance on revaluation surplus account associated with this asset is transferred off the revaluation surplus account to a Disposal Revaluation Surplus context account.

If the revalued asset holds a Grant Amount, the system applies a "grant depreciation" amount to the asset cost and writes off the remaining part of the grant to unrecognized grant (liability account). If the revaluation is not posted in the beginning of the year, depreciation calculation for the following periods should treat revaluation in the same way as any other activity that changes the asset cost.

Use the landing page of the application to view existing asset revaluations or enter a new one.


In this article, we will cover creating.

1. From the main menu, navigate to Financial Management > Asset Management > General Operations > Asset Revaluation Entry.

The Asset grid displays information about your current assets. You can right-click an asset to open **Asset Entry** or **Asset Tracker** for the asset.

- 2. Select the asset you want to revalue. The Asset Revaluation grid displays existing asset revaluations for that asset.
- 3. Select **New** to enter a new asset revaluation.






- 4. On the Details card, enter the **Valuation Date**. This is the actual date of the new valuation. By default, this is the apply date but you change it.
- 5. Enter the date you want to apply the asset revaluation and a description.
- 6. Enter the new book value for the asset in the Value field.
- 7. Select the **Ready to Post** check box if you want to post the revaluation to the Asset Tracker.




- 8. On the Register List card, enter the new estimated life for the asset and select whether this amount is in years or periods.
- 9. Enter the residual value for the asset. This cannot be less than the book value.





- 10. The default **Depreciation on Disposal/Revaluation** value comes from the asset but you can change it.
  - Prorate to Apply Date Calculate depreciation based on depreciation convention.
  - Full Month Always apply full month of depreciation.
  - None Do not depreciate the asset.



11. Select Save.

After you enter an asset revaluation and it is ready to post, you can post it using the Asset Posting Process. To learn more, refer to Running the Asset Posting Process.



# Running the Asset Posting Process

Run the **Asset Posting Process**to post asset activities (Additions, Impairments, Disposals, and Depreciations) based on the posting process options selected.

You can run this process as many times as required in a single period. The application posts the calculated depreciation for the newly calculated depreciation records. The posting process also posts the net change (if any) between what was previously posted and what will now be calculated.

To post an asset activity, some conditions must be true:

- The asset must be active, and must be assigned to an asset group.
  - The GL accounts of the assigned asset group must be valid.
  - If an asset class is used, then the Provision GL Account, the Depreciation Account, and the Cost Account inherit the division from the asset class. Therefore, those account combinations must be valid.
- The Ready to Post check box must be selected.
- The posting date must be in an open fiscal period.
  - The activity will not be posted if the open fiscal period for the activity is after the **Period**on the posting window.
  - The activity will not be posted if the open fiscal period for the activity is in a year different from the Year on the posting window.

The **Selection** parameters include:

- Starting Date Select the starting date of the posting period. You can also set up this process to run following a regular schedule. To do this, select the **Dynamic** check box.
- Ending Date Select the ending date of the posting period. You can also set up this process to run following a regular schedule. To do this, select the **Dynamic** check box.
- Dynamic Select this check box to run the process by a dynamic option rather than by a
  specific date. After you select this check box, the date field displays a list of dynamic options
  instead of the calendar. If you select this check box, you should also select a schedule in the
  Schedule field that works with the option you chose in the date field, and then select the
  Recurring check box next to the Schedule field.
- Group Activities Select how to group posted assets in GL Journal.
- Include Outdated Activities Select this check box if you want to include outdated activities in the posting process.
- Include Child Assets Select this check box if you want to include the child assets linked to
  the asset or asset group in the posting process.



- Select the asset activities to post:
  - Post Additions Posts all new assets acquired during the selected period.
  - Post Impairments Post all market value asset changes that occurred during the selected period.
  - Post Revaluations Post revaluation transactions for the selected period.
  - Post Disposals Posts all assets you are removing during the selected period.
  - Post Depreciation Post depreciation entries calculated for the selected period.
- Filter Use these fields to select specific Assets and Asset Groups for the posting process.
- Schedule Define when to run the process. If you select something other than Now, the Recurring check box is available.
- Recurring Select this check box if you want the report to run on a repeating basis.

#### To run the process:

- 1. From the main menu, go to Financial Management > Asset Management > General Operations > Asset Posting Process.
- 2. Select the parameters you want to use for the process.
- 3. Select **Process**.




# Closing Asset Period / Year

Close Asset Period / Year lets you close asset periods and years for a specified asset register. In its simplest form, an asset register is a detailed list of all your business assets.

Let's suppose that the only asset linked to one of your asset registers is being transferred to another register. As a result, you need to close the asset periods and year for this asset register.

**Tip**: Close Asset Period / Year is similar to the Close Fiscal Period / Year program available in the General Ledger module.

After you select an asset register, the app shows the associated calendar and current year. If necessary, you can enter a different Fiscal Year/Suffix. Once the year is selected, the **Fiscal Periods** grid populates with all periods attached to the calendar (with the exception of closing periods).



Manually close a period by selecting the **Closed** check box in the **Closed Period** column. When you select the Closed check box, the app verifies there are no unposted activities recorded for this



period. If unposted activities exist, the application shows an error message informing you there are unposted activities. In that case, the Closed check box automatically clears.

The period following the last closed period becomes the current asset period.

From the Overflow menu, you can select **Asset Year End Process**.



# Reports

This section describes some key reports used to review asset transactions. You can run these reports whenever needed.



# Generating the Asset Depreciation Report

Generate the **Asset Depreciation Report**to view depreciation for an asset register during a fiscal year and period time range.

#### The **Selection** parameters include:

- Asset Register The asset register that will be the basis for the report.
- Fiscal Calendar The fiscal calendar that is the basis for the report.
- Fiscal Year The fiscal year that is the basis for the report
- Fiscal Period The beginning and end range of the fiscal period for the report.
- Include Child Assets Select to include child assets the depreciation recalculation.
- Print Inactive Select to include inactive assets in the report.
- Print Summary Select to print the report in a summarized form.
- **Filter** Informs you whether you used filters or not. After you select a specific filter option, the fields located in this pane display values depending on whether you filtered (Some Selected) or you did not (All Selected).
- Report Style Select the report style option you want to use to run this report.
- Schedule Indicates when you want to print the report. If you select something other than Now, the Recurring check box is available.
- Archive Period Time period you want to keep the report in the System Monitor. The default is 0 Days, meaning that the report will be deleted from the monitor shortly after being printed.
  - After the Archive Period passes, the report is purged from the system. When a report is exactly purged is determined by a combination of the date/time the report generates, the number of days set in the report's Archive Period, and the Report Purge Frequency setting. The Report Purge Frequency is defined in the System Agent within its Task Agent Purge Settings.
- User Description Describes a specific report run. The entered description displays in the System Monitor.
- **Print Report Parameters** Indicates that the report selection criteria is printed as an appendix to the report.
- **Recurring** Select this check box if you want the report to run on a repeating basis. The check box is only available if you select a schedule other than Now.

#### To generate the report:

- From the main menu, go to Financial Management > Asset Management > Reports > Asset Depreciation.
- 2. Select the parameters depending on what you want the report to display.
- 3. Select Print Preview.





# Generating the Asset Depreciation Forecast Report

Generate the Asset Depreciation Forecast Report to review and print out the full year depreciation value forecast by an asset register. The forecast displays regardless of whether you post depreciation or not. You can select a forecast of up to five years.

#### The **Selection** parameters include:

- Start Year The year from which the depreciation will start.
- Asset Register A unique identifier of the asset register you want to include in the report.
- Years The number of depreciation years. This is limited to five years.
- Filter Informs you whether you used filters or not. After you select a specific filter option, the fields located in this pane display values depending on whether you filtered (Some Selected) or you did not (All Selected).
- Sort By Select whether you want to sort the report by Asset or Asset Group.
- Schedule Indicates when you want to print the report. If you select something other than Now, the Recurring check box is available.
- Report Style Select the report style option you want to use to run this report.
- Archive Period Time period you want to keep the report in the System Monitor. The default is 0 Days, meaning that the report will be deleted from the monitor shortly after being printed.
  - After the Archive Period passes, the report is purged from the system. When a report is exactly purged is determined by a combination of the date/time the report generates, the number of days set in the report's Archive Period, and the Report Purge Frequency setting. The Report Purge Frequency is defined in the System Agent within its Task Agent Purge Settings.
- Recurring Select this check box if you want the report to run on a repeating basis. The check box is only available if you select a schedule other than Now.
- User Description Describes a specific report run. The entered description displays in the System Monitor.

#### To generate the report:

- 1. From the main menu, go to Financial Management > Asset Management > Reports > Asset **Depreciation Forecast.**
- 2. Select the report parameters.
- 3. Select Print Preview.





# Generating the Asset Labels Report

Generate the **Asset Labels Report** to review and print out Asset labels.

The Asset label includes the following information:

- Asset Code
- · Asset Description
- Asset Tag
- · Location Details:
  - Location
  - · Warehouse Code
  - Bin Number

#### The **Selection** parameters include:

- New Select if you want the report to include new assets.
- Disposed Select if you want the report to include disposed assets.
- Active Select if you want the report to include active assets.
- Inactive Select if you want the report to include inactive assets.
- Acquired Date (From) The first date of the range of dates to search for the acquired assets
  the report will include.
- Acquired Date (To) The last date of the range of dates to search for the acquired assets the
  report will include.
- Include Child Assets Select to include child assets in the report, among the assets you select using Filter.
- Filter Informs you whether you used filters or not. After you select a specific filter option, the fields located in this pane display values depending on whether you filtered (Some Selected) or you did not (All Selected).
- Report Style Select the report style option you want to use to run this report.
- **Schedule** Indicates when you want to print the report. If you select something other than **Now**, the Recurring check box is available.
- Archive Period Time period you want to keep the report in the System Monitor. The default is 0 Days, meaning that the report will be deleted from the monitor shortly after being printed.
  - After the Archive Period passes, the report is purged from the system. When a report is exactly purged is determined by a combination of the date/time the report generates, the number of days set in the report's Archive Period, and the Report Purge Frequency setting. The Report Purge Frequency is defined in the System Agent within its Task Agent Purge Settings.
- **Recurring** Select this check box if you want the report to run on a repeating basis. The check box is only available if you select a schedule other than Now.



• **User Description** - Describes a specific report run. The entered description displays in the System Monitor.

#### To generate the report:

- 1. From the main menu, go to **Financial Management > Asset Management > Reports > Asset Labels**.
- 2. Select the report parameters.
- 3. Select **Print Preview**.



# Generating the Asset Overview Report

Generate the Asset Overview Report to review and print out the status of your assets, per Asset Register. The report displays asset costs and asset activities, including depreciation.

#### The **Selection** parameters include:

- Asset Register The asset register associated with the asset.
- Print Options Select what you want to display in the report. For example, if you want the report to display in a Summary form, select the Print Summary check box. The Summary version displays the total effect of all activities per an activity type. The Detailed version prints all the activities.
- Filter Informs you whether you used filters or not. After you select a specific filter option, the fields located in this pane display values depending on whether you filtered (Some Selected) or you did not (All Selected).
- Report Style Select the report style option you want to use to run this report.
- Schedule Indicates when you want to print the report. If you select something other than Now, the Recurring check box is available.
- Archive Period Time period you want to keep the report in the System Monitor. The default is 0 Days, meaning that the report will be deleted from the monitor shortly after being printed.
  - After the Archive Period passes, the report is purged from the system. When a report is exactly purged is determined by a combination of the date/time the report generates, the number of days set in the report's Archive Period, and the Report Purge Frequency setting. The Report Purge Frequency is defined in the System Agent within its Task Agent Purge Settings.
- Recurring Select this check box if you want the report to run on a repeating basis. The check box is only available if you select a schedule other than Now.
- User Description Describes a specific report run. The entered description displays in the System Monitor.

#### To generate the report:

- 1. From the main menu, go to Financial Management > Asset Management > Reports > Asset Overview.
- 2. Select the report parameters.
- 3. Select Print Preview.





# Generating the Asset Annual Schedule Report

Generate the **Asset Annual Schedule Report** to view and print out total change in asset cost and depreciation per transaction type for the given fiscal year.

The report works with the **Asset Transactions** data. Kinetic supports the following Asset transactions:

- Additions
- · Impairments
- Disposals
- · Depreciations
- Revaluations

The Selection parameters include:

- Asset Register Select an asset register from a list of available registers.
- Data Selection Specifies data selection mode for the report. The options include:
  - By Fiscal Year If selected, the Fiscal Year, Fiscal Year Suffix, and Cut-off Date fields become available. This is the default option.
  - By Date Range If selected, the Start Date and End Date fields become available.
- Fiscal Year This is the fiscal year. The default value is the current year in the selected register's calendar.
- Suffix The fiscal year suffix if one exists.
- Cut-off-date The latest date from which to select asset transactions. The default value is the last day of the selected fiscal year.
- Start Date The start date of the report. This field becomes available when you select the By
  Date Range option in the Data Selection field. The Start Date must be earlier than the End
  Date. Start and end dates can belong to different fiscal years.
- End Date The end date of the report. This field becomes available if you select the By Date Range option in the Data Selection field. The End Date must be later than the Start Date.
   Start and end dates can belong to different fiscal years.
- **Print Details** If selected, the report prints in the **Detailed** layout. If clear, the report prints in the **Summary** layout.
- Group By Select how you want to group the report. You can use the Report Category, Asset Group, and Asset options.
- GL Posting Status Select the status you want the report to display. For example, if you want
  the process to generate only asset transactions posted to the General Ledger (GL), select the
  Only Posted to the GL option.



- **Filter** Informs you whether you used filters or not. After you select a specific filter option, the fields located in this pane display values depending on whether you filtered (Some Selected) or you did not (All Selected).
- Report Style Select the report style option you want to use to run this report.
- Schedule Indicates when you want to print the report. If you select something other than Now, the Recurring check box is available.
- Archive Period Time period you want to keep the report in the System Monitor. The default is 0 Days, meaning that the report will be deleted from the monitor shortly after being printed.
  - After the Archive Period passes, the report is purged from the system. When a report is exactly purged is determined by a combination of the date/time the report generates, the number of days set in the report's Archive Period, and the Report Purge Frequency setting. The Report Purge Frequency is defined in the System Agent within its Task Agent Purge Settings.
- **Recurring** Select this check box if you want the report to run on a repeating basis. The check box is only available if you select a schedule other than Now.
- Print Report Parameters If selected, the report selection criteriais print as an appendix to the
  report. This setting enables you to re-create the contents of a printed report by selecting the
  same parameters and report options, which were used to create the original report (if the
  report data has not been updated in Kinetic since the original report was printed).
- User Description Describes a specific report run. The entered description displays in the System Monitor.

#### To generate the report:

- 1. From the main menu, go to Financial Management > Asset Management > Reports > Asset Annual Schedule.
- 2. Select the report parameters.
- 3. Select Print Preview.



